Creating New Instances

The Radiant documentation has moved to https://docs.ncsa.illinois.edu/systems/radiant/. Please update any bookmarks you may have. Click in the link above if you are not automatically redirected in 5 seconds.

This guide explains how to create a virtual machine (VM) using Radiant's OpenStack Dashboard (Horizon). There is also a description of how to access your new VM and how to mount persistent storage volumes.

Quick highlights:

- · If your VM uses a volume (default) it will count against your flash quota
- You need to select Configuration Drive in the configuration tab

Table of contents

VM Creation

Defaults

Name your instance

Launch Instance		:	×
Details	Please provide the initial hostname for the instance, the availability zone where count. Increase the Count to create multiple instances with the same settings.	e it will be deployed, and the instance	0
Source *	Instance Name *	Total Instances	
Flavor *	my-first-machine	(20 Max)	
	Description	5%	
Networks			
Network Ports	Availability Zone	0 Current Usage	
Security Groups	nova 🗸	19 Remaining	
Key Pair	Count *		
Configuration	1		
Server Groups			
Scheduler Hints			
Metadata			
× Cancel	< Bac	k Next > A Launch Instance	

Source

Select base OS and where to run. The default is to create a new volume. This will count against your flash storage quota as well as take up one of your volumes. This is good if you want your data to persist after you tell openstack to delete your instance. If you want to create an instance that can be rebooted (maybe migrated), you can select "No" for this. If you create a new volume you can pick the size of the volume, if you selected no, it will use the default size for the Flavor (see point 3). You will also need to select the base image you start with. This list might change over time.

Details	(image snapshot), a volume or a	used to create an instance. ' volume snapshot (if enabled	You can use an im d). You can also ch	age, a snap oose to use	shot of an instan persistent stora	ce ge by
	Select Boot Source		Create New Vol	ume		
Flavor *	Image	~	Yes No			
Networks *	Allocated					
Network Ports	Name	Updated	Size	Тур	visibility	
Security Groups	> CentOS-7-GenericCloud-La	atest 5/8/20 12:3	0 PM 8.00	GB rav	v Public	•
Key Pair	✓ Available ②					Select o
Configuration	Q Click here for filters or fu	ll text search.				:
Server Groups	Name	Updated	Size	Туре	Visibility	
Scheduler Hints	> cirros-0.5.1-x86_64	5/8/20 12:30 PM	112.00 MB	raw	Public	•
					D. L.F.	

Flavor

Next you select the flavor (again this list might change over time). If you select a flavor that would use to many resources you will see a yellow exclamation sign next to it. If you selected No for the volume create in the source screen, the volume will be the same size as the root disk.

Launch Instance								×
Details	Flavors manage Allocated	the sizing fo	r the compute	e, memory and	storage capacity	of the instance.		•
Source	Name	VCPUS	RAM	Total Disk	Root Disk	Ephemeral Disk	Public	
Flavor	> m1.mediun	n 2	4 GB	40 GB	40 GB	0 GB	Yes	•
Networks *	✓ Available	6					s	elect one
Network Ports	Q Click her	e for filters o	r full text sear	ch.			-	×
Security Groups	Name	VCPUS	RAM	Total Disk	Root Disk	Ephemeral Disk	Public	
Key Pair	> m1.tiny	1	512 MB	1 GB	1 GB	0 GB	Yes	•
Configuration	> m1.small	1	2 GB	20 GB	20 GB	0 GB	Yes	•
Scheduler Hints	> m1.large	4	8 GB	80 GB	80 GB	0 GB	Yes	•
Metadata	> p1.large	10	62.5 GB	64 GB	64 GB	0 GB	Yes	•
	> p1.xlarge	10	117.19 GB	64 GB	64 GB	0 GB	Yes	•
* Cancel					<	Back Next >	Launch Ir	nstance

Networks

Next we select the network. You may see a few network options to choose from here. Look for a network that is <projectname>-net, for example bbdf-net, where bbdf is the name of your project. Do NOT pick ext-net on this page, if you do your instance will fail to be created. By default the <projectnam e>-net network does not allow for external connections. Only other hosts on that same network will be able to reach this machine. This is fine for a host that only needs to be reachable from other hosts within your network. If you need to setup a host that is reachable from outside your network, you will need to associate a floating IP address to your instance. This is setup after an instance is created (see below).

Details	Networks provide	the communication channels for	instances in the cloue	d. Select networ	ks from those lis	ted he
Source	Net	work Subnets Associate	d Shared	Admin State	Status	.00.00
lavor	≑ 1 > bbd	-net bbdf-subnet	No	Up	Active	4
Networks						
letwork Ports	✓ Available			5	Select at least or	e netv
ecurity Groups	Q Click here	for filters or full text search.				
(ey Pair	Network	Subnets Associated	Shared	Admin State	Status	
Configuration	> ext-net	ext-net-subnet	Yes	Up	Active	1
erver Groups						
cheduler Hints						
letadata						

Network Ports

Can be ignored

Security Groups

Security Groups will allow you to add additional security groups. It is good to add remote SSH to allow you to ssh to the host. If a port is not opened in the security group, you will not be able to reach that host on that port. This is basically a firewall that blocks all incoming traffic by default.

Launch Instance			×
Details	Select the security groups to la	unch the instance in.	0
Source	✓ Allocated ② Name	Description	
Flavor	> default	Default security group	•
Networks	> remote SSH	Allow ssh traffic from the internet	•
Network Ports	✓ Available ①		Select one or more
Security Groups	Q Click here for filters or fi	ull text search.	×
Configuration	Name	Description	
Server Groups	> remote HTTP/HTTPS	Allow web traffic from the internet	•
Scheduler Hints			
Metadata			
× Cancel		< Back Next >	Launch Instance

Key Pair

Next you need to either select an existing key pair or create a new one. If you do not select a key pair, you will not be able to SSH into this machine. The default behavior is for most base images to not have a user with a password. See the end for some common usernames for each image. If you create a new key, make sure to copy the private key and save it to disk. It's best to save it as **.pem** file on your workstation/laptop, as your OS won't attempt to be helpful and add extra formatting if you give it a different extension. Save it in a path where you will have easy access for your later ssh sessions. **DO NOT lose this file, or you will have to start your VM instance again from scratch!**

Create Key F	Pair						×
Key Pairs are how only include alph	w you login to your insta anumeric characters, sp *	nce after it is paces, or das	s launched. shes.	Choose a	a ke	y pair name you will recognize. Na	ames may
test							
Key Type [*]							
SSH Key							*
			Create H	Keypair		Copy Private Key to Clipboard	Done
Launch Instance					×		
Details	A key pair allows you to SSH into your newly o pair, or generate a new key pair.	created instance. You ma	y select an existing ke	y pair, import a key			
Flavor	Allocated Displaying 1 item						
Networks	Name	Туре					
Network Ports	> test	ssh			¥		
Key Pair	Displaying 1 item						
Configuration	✓ Available ○			Selec	t one		
	Q Click here for filters or full text search.				×		
Selver Groups	Displaying 0 items						
Matadata	Name	Type ≑					
พษณนสิน		No items to display.					
	Displaying 0 items						
¥ Cancel			(Back News)		000		

Configuration

The next screen allows you to configure the new machine on boot. You can use this to install programs, or do anything else on first boot. YOU NEED TO SELECT CONFIGURATION DRIVE HERE. The default is for it to be unchecked. If you leave it unchecked your key, and/or startup script will not work!

Details	You can customize your instance after it has launched usin analogous to "Leer Data" in other systems	g the options available here. *Customization Script* is
Source	Load Customization Script from a file	
Flavor	Customization Script (Modified)	Content size: 31 bytes of 16.00 K
Networks	#!/bin/bash	
Network Ports	echo "HELLO WORLD"	
Security Groups		
Key Pair		
Configuration	Disk Partition	
Server Groups	Automatic	```
Scheduler Hints	Configuration Drive	
Metadata	_	
¥ Cancel		(Back Next) A Launch Instance

Server Groups / Scheduler Hints / Metadata

You can leave these 3 sections as is. And you can now launch your instance. It should be ready in a few minutes, you can see it listed in the dashboard under Instances.

Assigning a Floating IP to your Instance (Optional)

If your instance needs to be reachable from the internet, you need to assign a floating IP address to it. If that is not needed on your instance you can skip this section.

Locate your instance in the list and click the down arrow button in the 'actions' column. From the drop down list select 'Associate Floating IP'. From the 'IP A ddress' selection box, pick an available IP from the list, this will be the floating IP for your instance. For 'Port to be associated' you can usually leave the default, but if you have multiple interfaces you can select the appropriate port. Then click the 'Associate' button.

Accessing your instance

Once the instance is Active and Running you should be able to SSH to it. You'll just need the IP address, the username, and the key (you did save it right?)

You would ssh to your instance using: ssh -i test.pem centos@IP_ADDRESS, where

- IP_ADDRESS is the IP address assigned to your instance. If you assigned a floating IP you'd want to use that address when SSHing from an
 external host, if you are SSHing from a host on your project's own network you can use the IP assigned on the project interface
- test.pem is the key you saved
- centos is the username, depending on the OS you picked this may be different, see that table in the 'Troubleshooting' section below for some common alternatives

If you might get an error that the permissions are too open you can change them using chmod 600 key.

Running in the system

First thing to do is make sure you mount in Taiga bulk storage if you want to use more diskspace. Each instance only has a little storage (40GB) that is primarily used for the OS. You can mount additional Taiga Bulk storage via NFS using:

mount -t nfs taiga-nfs.ncsa.illinois.edu:/taiga/ncsa/radiant/bbXX /mnt/point
Where bbXX is your unique Radiant project code and /mnt/point is the target mount path.

This will make your bulk storage space available on your machine. It will take a few minutes from when your machine boots, until the space can be mounted.

Change your root password

Once you're able to log in remotely as root, be sure to change the root password on your instance. This allows you to access your instance's console via the web interface if you can't ssh in later for some reason.

Ensure that you create a secure password and that you save it in an appropriate password manager sudo passwd

Troubleshooting

Trouble accessing systems.

- Did you add Remote SSH as a security group? If not you can edit the security groups and add the group to the instance.
- Does the ssh attempt claim that the key is an "invalid format"? the .pem file must contain no extra characters or line breaks in a text editor, it should look like this:

----BEGIN RSA PRIVATE KEY-----

MIIEowIBAAKCAQEAmN7qws0+gxKKczyFkkngz+uoAzmcHm5HTLvuOz80atQhAlG1 EzqjI9IDKTZtM7lhvj+6lwCeieLqn8J6Y5/T25k8nLb8pufJvXgtfl8b4gv/Y/KX ULfHhVNE+qz195FmkaJwxe5TFtWvlpDRxdOgCfKrLvgaWI+vrUXfhfms16YRHHLb UrnH/vyo3/m6T1rspNdFgCwXy4e1LBEVuAqj4uxqkBNDKGeeAuBJ5dBxMJaD+aWZ dz3GejoXWJ1MvGAjmZ/oQghgvmz18grpw6OeVx1CTlQ2KoRyaOUW8cCum5BYQv9v zX2KDw1PCHdZKZeAZq9Qia98mlvEPdpaN+0dIQIDAQABAoIBAQCKOg62hBWBOTOd TV1N0KWJ/ADYoa/ryDWKSef5BGRJ7nPGgBEmSQAYtJ4NFtyZR4f9Gezi+zlfXqJe QOCf0nYje6TV45QCa1X8j307Zk51D/om6sUtxG+Ru6CEte/e8kd3ahVks8HHxQJX ${\tt N62mnlt4g0eMWeSgrZPhLmwV3ZPVLntCUIqiEVYmfSMAmuSruNXKTt3JEYCy7wbo}$ e0+HBHem16l1v+ADf8vKs3wfQ6L7jSXK9ihN4EFFbb+MxQXZCFCWMZMfWkpV7qZw UiYjjnLz97fF1d38IJCgZJ/qJTHuIoAxbA2pckXQCT+ttrFdjMo6lsKC5iZ7xcBO ryHN97ZtAoGBAMiPWLUWMfn9+kXKTYXBmm8gRqRQsHB0KIgQmo1oZW11QMRsc4Ys WiWWRYfkup8x+cp+S8TUxfe7LWsjWa718q9QE8g9wLvLypm16WkxnQsCTz/yW7QG HP33G8zq+FLrncdXN7/77gYNAQJ56Zks0jMl9NQgHP4roOazmQ1ltWrHAoGBAMMg 1smbuORi/8M+vT4EJx5oXYgz/eun+/1pv9xE7oZmubw5wzuGY5sjREWVnxnNFkIV rfHNorI0jc6JeeG4WivcJ7fDE3bTiNKz8JJbcavAIxNpjNQO9QkxCWjtt6k0TE8K gvasYxrQb8pSR3nSqis31WY2mg+W/u5nTeHW/BDXAoGAAl5fB9R5RqCPQh+/hqLg tgtFik9BpjJZADJiAOWIvSADAc7eFmmTrvn1XEOBSLwIXTHcpzh0Fhbp1GgYeQ6C jTt+4FCKZC11+SbC2PEzD5w5X2H3X0rrMLyoYWUtBZ2uwVnwWJ4bE4s3xdW2wo5Z KZ17JL40WXQedFsOpa/b0qUCgYAVtH9v6ayFayW8GCyAy4F2dnGBBxeFsSfsNIEt BVXrCV47u8klw+sshJ3Bh8Us341MSJESxqcEX6gug0hVfWY6XsDkRgTSQPGFTpLC FP3t9u9v51vM8uT64sODMn4tii261RaATeiwQONOhByDRpW7PPi15/j3Jvqwljkp l/pt/QKBgFTlbV9jkl7Pke4NC+yCrhe79qTvJrLJ8hFJwnw+zGdrlG2tyWK6J7Ar lSPGPMYLo7ExA2J4JxsNes1PVHpXiXIelHUsiQQDaz/RBzMJgpds3M1MU5Nl0HtW r9M2paxYkiUqsM5ojDktjB0IpxNG4mWzL07D4MW4YzxCbRWU/kA6 ----END RSA PRIVATE KEY-----

• Did you use the right username? The following is a list of known usernames:

OS	username
CentOS	centos
Ubuntu	ubuntu
CoreOS	core
RedHat	cloud-user
Rocky	rocky/cloud-user

Trouble in the system

• I'm out of diskspace. Make sure to mount storage condo for all your data. You only have a small amount of root storage.